

Installing Window Vision Remote Pro version 5.30 on Windows 7

Please read all of the instructions before starting:

Due to the drastic changes Windows 7 incorporates over previous operating systems, past versions of the Remote software will not run in Windows 7. The steps below will walk you through installing our latest software version, but before continuing, any installed copies of the Remote software on the computer in question **MUST BE UNINSTALLED FIRST**.

If you have not downloaded the installation files, please obtain them from here:

<http://www.silicor.com/download/full/WV530G5woDN.zip>

We apologize for the size of the download, in the near future we will be offering a smaller download package. Once the download is complete, please extract all the files and then run the setup.exe file. When asked, use the following serial key: wv3h100026937987.

On the next page, be certain to select REMOTE INSTALLATION before clicking the 'next' button. After the installation is complete you will be asked to reboot your computer, if you have any open files/programs it is recommended to save your data before rebooting.

64-bit Windows

If when you run Window Vision you received a message indicating that IPV32_20.dll could not be found, please do the following:

1. Open Computer
2. Open the C: drive and then open Program Files (x86)
3. Open Common Files and look for a folder called Ipix
4. Select and copy the Ipix folder
5. Go back to the C: drive and open Program Files and then Common Files
6. Paste the Ipix folder inside of here
7. Close the Window and run Window Vision Remote